

DragonFlyBSD - Bug #744

rcstart broken with dhclient

07/26/2007 10:09 PM - corecode

| | |
|--|----------------------------------|
| Status: Closed | Start date: |
| Priority: Normal | Due date: |
| Assignee: | % Done: 0% |
| Category: | Estimated time: 0.00 hour |
| Target version: | |
| Description hey, rcstart doesn't work as desired anymore: %rcstart dnptd dnptd depends on dhclient, current state: % I guess that's because of the dhclient change. I can't use rcrestart dhclient either anymore. cheers simon | |

History

#1 - 06/21/2006 12:07 AM - bastyaeltars

On Fri, 27 Jul 2007 00:03:56 +0200

"Simon 'corecode' Schubert" <corecode@fs.ei.tum.de> wrote:

Confirming. rcrestart does not work at all here.

#2 - 06/21/2006 12:07 AM - swildner

Hmm, I'm not sure about a solution. The new dhclient script expects the interface as an argument (as in "/etc/rc.d/dhclient start rl0") but rc{run,start,...} doesn't support that.

Sascha

#3 - 06/21/2006 12:07 AM - tuxillo

```
I've tried inside an vkernel:
vkernel-leaf# rcstop dnptd
Stopping dnptd.
vkernel-leaf# rcstart dnptd
Running /etc/rc.d/dnptd start
Starting dnptd.
vkernel-leaf# rcrestart dnptd
Stopping dnptd.
Starting dnptd.
vkernel-leaf#
```

It worked fine for me.

#4 - 06/21/2006 12:07 AM - corecode

seems to work now.

#5 - 06/21/2006 12:07 AM - qhwt+dfly

```
> I've tried inside an vkernel:
> vkernel-leaf# rcstop dnptd
> Stopping dnptd.
> vkernel-leaf# rcstart dnptd
```

But I'm afraid this is about dhclient script, not about dnptd... :)

#6 - 06/21/2006 12:07 AM - ahuate.devel

But corecode reproduced it doing a rcrestart on dnptd, and now it doesn't seem to happen.
Can you reproduce it?

2009/8/26 YONETANI Tomokazu <qhwt+dfly@les.ath.cx>:

```
>> I've tried inside an vkernel:
>> vkernel-leaf# rcstop dnptd
>> Stopping dnptd.
>> vkernel-leaf# rcstart dnptd
>
> But I'm afraid this is about dhclient script, not about dnptd... :)
>
```

#7 - 06/21/2006 12:07 AM - qhwt+dfly

A-ha, OK, it *was* about dnptd, and was apparently fixed by 6af26f98 because dnptd requires NETWORKING, which used to require dhclient back then.
And dhclient won't start because it's marked as `nostart`...

On Wed, Aug 26, 2009 at 02:41:45PM +0200, Antonio Huete Jimenez wrote:

```
> But corecode reproduced it doing a rcrestart on dnptd, and now it
> doesn't seem to happen.
> Can you reproduce it?
>
> 2009/8/26 YONETANI Tomokazu <qhwt+dfly@les.ath.cx>:
> >> I've tried inside an vkernel:
> >> vkernel-leaf# rcstop dnptd
> >> Stopping dnptd.
> >> vkernel-leaf# rcstart dnptd
> >>
> > But I'm afraid this is about dhclient script, not about dnptd... :)
> >>
```